

**NAME**

**sudo**, **sudoedit** - execute a command as another user

**SYNOPSIS**

**sudo -h | -K | -k | -V**

**sudo -v [-ABkNnS] [-a type] [-g group] [-h host] [-p prompt] [-u user]**

**sudo -l [-ABkNnS] [-a type] [-g group] [-h host] [-p prompt] [-U user] [-u user] [command [arg ...]]**

**sudo [-ABbEHnPS] [-a type] [-C num] [-c class] [-D directory] [-g group] [-h host] [-p prompt]**

**[-R directory] [-r role] [-t type] [-T timeout] [-u user] [VAR=value] [-i | -s] [command [arg ...]]**

**sudoedit [-ABkNnS] [-a type] [-C num] [-c class] [-D directory] [-g group] [-h host] [-p prompt]**

**[-R directory] [-r role] [-t type] [-T timeout] [-u user] file ...**

**DESCRIPTION**

**sudo** allows a permitted user to execute a *command* as the superuser or another user, as specified by the security policy. The invoking user's real (*not* effective) user-ID is used to determine the user name with which to query the security policy.

**sudo** supports a plugin architecture for security policies, auditing, and input/output logging. Third parties can develop and distribute their own plugins to work seamlessly with the **sudo** front-end. The default security policy is *sudoers*, which is configured via the file */etc/sudoers*, or via LDAP. See the *Plugins* section for more information.

The security policy determines what privileges, if any, a user has to run **sudo**. The policy may require that users authenticate themselves with a password or another authentication mechanism. If authentication is required, **sudo** will exit if the user's password is not entered within a configurable time limit. This limit is policy-specific; the default password prompt timeout for the *sudoers* security policy is 5 minutes.

Security policies may support credential caching to allow the user to run **sudo** again for a period of time without requiring authentication. By default, the *sudoers* policy caches credentials on a per-terminal basis for 5 minutes. See the *timestamp\_type* and *timestamp\_timeout* options in *sudoers(5)* for more information. By running **sudo** with the **-v** option, a user can update the cached credentials without running a *command*.

On systems where **sudo** is the primary method of gaining superuser privileges, it is imperative to avoid syntax errors in the security policy configuration files. For the default security policy, *sudoers(5)*, changes to the configuration files should be made using the *visudo(8)* utility which will ensure that no syntax errors are introduced.

When invoked as **sudoedit**, the **-e** option (described below), is implied.

Security policies and audit plugins may log successful and failed attempts to run **sudo**. If an I/O plugin is configured, the running *command*'s input and output may be logged as well.

The options are as follows:

**-A, --askpass**

Normally, if **sudo** requires a password, it will read it from the user's terminal. If the **-A** (*askpass*) option is specified, a (possibly graphical) helper program is executed to read the user's password and output the password to the standard output. If the `SUDO_ASKPASS` environment variable is set, it specifies the path to the helper program. Otherwise, if `sudo.conf(5)` contains a line specifying the askpass program, that value will be used. For example:

```
# Path to askpass helper program
Path askpass /usr/X11R6/bin/ssh-askpass
```

If no askpass program is available, **sudo** will exit with an error.

**-a type, --auth-type=type**

Use the specified BSD authentication *type* when validating the user, if allowed by `/etc/login.conf`. The system administrator may specify a list of sudo-specific authentication methods by adding an "auth-sudo" entry in `/etc/login.conf`. This option is only available on systems that support BSD authentication.

**-B, --bell**

Ring the bell as part of the password prompt when a terminal is present. This option has no effect if an askpass program is used.

**-b, --background**

Run the given *command* in the background. It is not possible to use shell job control to manipulate background processes started by **sudo**. Most interactive *commands* will fail to work properly in background mode.

**-C num, --close-from=num**

Close all file descriptors greater than or equal to *num* before executing a *command*. Values less than three are not permitted. By default, **sudo** will close all open file descriptors other than standard input, standard output, and standard error when executing a *command*. The security policy may restrict the user's ability to use this option. The *sudoers* policy only permits use of the **-C** option when the administrator has enabled the `closefrom_override` option.

**-c class, --login-class=class**

Run the *command* with resource limits and scheduling priority of the specified login *class*. The *class* argument can be either a class name as defined in */etc/login.conf*, or a single '-' character. If *class* is -, the default login class of the target user will be used. Otherwise, the *command* must be run as the superuser (user-ID 0), or **sudo** must be run from a shell that is already running as the superuser. If the *command* is being run as a login shell, additional */etc/login.conf* settings, such as the umask and environment variables, will be applied, if present. This option is only available on systems with BSD login classes.

**-D directory, --chdir=directory**

Run the *command* in the specified *directory* instead of the current working directory. The security policy may return an error if the user does not have permission to specify the working directory.

**-E, --preserve-env**

Indicates to the security policy that the user wishes to preserve their existing environment variables. The security policy may return an error if the user does not have permission to preserve the environment.

**--preserve-env=list**

Indicates to the security policy that the user wishes to add the comma-separated list of environment variables to those preserved from the user's environment. The security policy may return an error if the user does not have permission to preserve the environment. This option may be specified multiple times.

**-e, --edit**

Edit one or more *files* instead of running a *command*. In lieu of a path name, the string "sudeedit" is used when consulting the security policy. If the user is authorized by the policy, the following steps are taken:

1. Temporary copies are made of the files to be edited with the owner set to the invoking user.
2. The editor specified by the policy is run to edit the temporary files. The *sudoers* policy uses the SUDO\_EDITOR, VISUAL and EDITOR environment variables (in that order). If none of SUDO\_EDITOR, VISUAL or EDITOR are set, the first program listed in the *editor* sudoers(5) option is used.
3. If they have been modified, the temporary files are copied back to their original location and the temporary versions are removed.

To help prevent the editing of unauthorized files, the following restrictions are enforced unless explicitly allowed by the security policy:

- Symbolic links may not be edited (version 1.8.15 and higher).
- Symbolic links along the path to be edited are not followed when the parent directory is writable by the invoking user unless that user is root (version 1.8.16 and higher).
- Files located in a directory that is writable by the invoking user may not be edited unless that user is root (version 1.8.16 and higher).

Users are never allowed to edit device special files.

If the specified file does not exist, it will be created. Unlike most *commands* run by *sudo*, the editor is run with the invoking user's environment unmodified. If the temporary file becomes empty after editing, the user will be prompted before it is installed. If, for some reason, **sudo** is unable to update a file with its edited version, the user will receive a warning and the edited copy will remain in a temporary file.

**-g** *group*, **--group=group**

Run the *command* with the primary group set to *group* instead of the primary group specified by the target user's password database entry. The *group* may be either a group name or a numeric group-ID (GID) prefixed with the '#' character (e.g., '#0' for GID 0). When running a *command* as a GID, many shells require that the '#' be escaped with a backslash ('\'). If no **-u** option is specified, the *command* will be run as the invoking user. In either case, the primary group will be set to *group*. The *sudoers* policy permits any of the target user's groups to be specified via the **-g** option as long as the **-P** option is not in use.

**-H**, **--set-home**

Request that the security policy set the HOME environment variable to the home directory specified by the target user's password database entry. Depending on the policy, this may be the default behavior.

**-h**, **--help**

Display a short help message to the standard output and exit.

**-h** *host*, **--host=host**

Run the *command* on the specified *host* if the security policy plugin supports remote *commands*. The *sudoers* plugin does not currently support running remote *commands*. This may also be used in conjunction with the **-l** option to list a user's privileges for the remote host.

**-i, --login**

Run the shell specified by the target user's password database entry as a login shell. This means that login-specific resource files such as *.profile*, *.bash\_profile*, or *.login* will be read by the shell. If a *command* is specified, it is passed to the shell as a simple *command* using the **-c** option. The *command* and any *args* are concatenated, separated by spaces, after escaping each character (including white space) with a backslash (```) except for alphanumeric characters, underscores, hyphens, and dollar signs. If no *command* is specified, an interactive shell is executed. **sudo** attempts to change to that user's home directory before running the shell. The *command* is run with an environment similar to the one a user would receive at log in. Most shells behave differently when a *command* is specified as compared to an interactive session; consult the shell's manual for details. The *Command environment* section in the *sudoers(5)* manual documents how the **-i** option affects the environment in which a *command* is run when the *sudoers* policy is in use.

**-K, --remove-timestamp**

Similar to the **-k** option, except that it removes every cached credential for the user, regardless of the terminal or parent process ID. The next time **sudo** is run, a password must be entered if the security policy requires authentication. It is not possible to use the **-K** option in conjunction with a *command* or other option. This option does not require a password. Not all security policies support credential caching.

**-k, --reset-timestamp**

When used without a *command*, invalidates the user's cached credentials for the current session. The next time **sudo** is run in the session, a password must be entered if the security policy requires authentication. By default, the *sudoers* policy uses a separate record in the credential cache for each terminal (or parent process ID if no terminal is present). This prevents the **-k** option from interfering with **sudo** commands run in a different terminal session. See the *timestamp\_type* option in *sudoers(5)* for more information. This option does not require a password, and was added to allow a user to revoke **sudo** permissions from a *.logout* file.

When used in conjunction with a *command* or an option that may require a password, this option will cause **sudo** to ignore the user's cached credentials. As a result, **sudo** will prompt for a password (if one is required by the security policy) and will not update the user's cached credentials.

Not all security policies support credential caching.

**-l, --list** If no *command* is specified, list the privileges for the invoking user (or the *user* specified by the **-U** option) on the current host. A longer list format is used if this option is specified multiple times and the security policy supports a verbose output format.

If a *command* is specified and is permitted by the security policy for the invoking user (or the, *user* specified by the **-U** option) on the current host, the fully-qualified path to the *command* is displayed along with any *args*. If **-I** is specified more than once (and the security policy supports it), the matching rule is displayed in a verbose format along with the *command*. If a *command* is specified but not allowed by the policy, **sudo** will exit with a status value of 1.

**-N, --no-update**

Do not update the user's cached credentials, even if the user successfully authenticates. Unlike the **-k** flag, existing cached credentials are used if they are valid. To detect when the user's cached credentials are valid (or when no authentication is required), the following can be used:

```
sudo -Nnv
```

Not all security policies support credential caching.

**-n, --non-interactive**

Avoid prompting the user for input of any kind. If a password is required for the *command* to run, **sudo** will display an error message and exit.

**-P, --preserve-groups**

Preserve the invoking user's group vector unaltered. By default, the *sudoers* policy will initialize the group vector to the list of groups the target user is a member of. The real and effective group-IDs, however, are still set to match the target user.

**-p prompt, --prompt=prompt**

Use a custom password prompt with optional escape sequences. The following percent ('%') escape sequences are supported by the *sudoers* policy:

%H

expanded to the host name including the domain name (only if the machine's host name is fully qualified or the *fqdn* option is set in *sudoers(5)*)

%h

expanded to the local host name without the domain name

%p

expanded to the name of the user whose password is being requested (respects the *rootpw*, *targetpw*, and *runaspw* flags in *sudoers(5)*)

%U

expanded to the login name of the user the *command* will be run as (defaults to root unless the **-u** option is also specified)

**%u**

expanded to the invoking user's login name

**%%**

two consecutive '%' characters are collapsed into a single '%' character

The custom prompt will override the default prompt specified by either the security policy or the SUDO\_PROMPT environment variable. On systems that use PAM, the custom prompt will also override the prompt specified by a PAM module unless the *passprompt\_override* flag is disabled in *sudoers*.

**-R directory, --chroot=directory**

Change to the specified root *directory* (see *chroot(8)*) before running the *command*. The security policy may return an error if the user does not have permission to specify the root directory.

**-r role, --role=role**

Run the *command* with an SELinux security context that includes the specified *role*.

**-S, --stdin**

Write the prompt to the standard error and read the password from the standard input instead of using the terminal device.

**-s, --shell**

Run the shell specified by the SHELL environment variable if it is set or the shell specified by the invoking user's password database entry. If a *command* is specified, it is passed to the shell as a simple command using the **-c** option. The *command* and any *args* are concatenated, separated by spaces, after escaping each character (including white space) with a backslash ('\') except for alphanumerics, underscores, hyphens, and dollar signs. If no *command* is specified, an interactive shell is executed. Most shells behave differently when a *command* is specified as compared to an interactive session; consult the shell's manual for details.

**-t type, --type=type**

Run the *command* with an SELinux security context that includes the specified *type*. If no *type* is specified, the default type is derived from the role.

**-U user, --other-user=user**

Used in conjunction with the **-l** option to list the privileges for *user* instead of for the invoking user. The security policy may restrict listing other users' privileges. When using the *sudoers* policy, the **-U** option is restricted to the root user and users with either the "list" privilege for the specified *user* or the ability to run any *command* as root or *user* on the current host.

**-T** *timeout*, **--command-timeout**=*timeout*

Used to set a timeout for the *command*. If the timeout expires before the *command* has exited, the *command* will be terminated. The security policy may restrict the user's ability to set timeouts. The *sudoers* policy requires that user-specified timeouts be explicitly enabled.

**-u** *user*, **--user**=*user*

Run the *command* as a user other than the default target user (usually **root**). The *user* may be either a user name or a numeric user-ID (UID) prefixed with the '#' character (e.g., '#0' for UID 0). When running *commands* as a UID, many shells require that the '#' be escaped with a backslash ('\'). Some security policies may restrict UIDs to those listed in the password database. The *sudoers* policy allows UIDs that are not in the password database as long as the *targetpw* option is not set. Other security policies may not support this.

**-V**, **--version**

Print the **sudo** version string as well as the version string of any configured plugins. If the invoking user is already root, the **-V** option will display the options passed to configure when **sudo** was built; plugins may display additional information such as default options.

**-v**, **--validate**

Update the user's cached credentials, authenticating the user if necessary. For the *sudoers* plugin, this extends the **sudo** timeout for another 5 minutes by default, but does not run a *command*. Not all security policies support cached credentials.

-- The -- is used to delimit the end of the **sudo** options. Subsequent options are passed to the *command*.

Options that take a value may only be specified once unless otherwise indicated in the description. This is to help guard against problems caused by poorly written scripts that invoke **sudo** with user-controlled input.

Environment variables to be set for the *command* may also be passed as options to **sudo** in the form *VAR=value*, for example *LD\_LIBRARY\_PATH=/usr/local/pkg/lib*. Environment variables may be subject to restrictions imposed by the security policy plugin. The *sudoers* policy subjects environment variables passed as options to the same restrictions as existing environment variables with one important difference. If the *setenv* option is set in *sudoers*, the *command* to be run has the SETENV tag set or the



*command* matched is **ALL**, the user may set variables that would otherwise be forbidden. See `sudoers(5)` for more information.

## COMMAND EXECUTION

When **sudo** executes a *command*, the security policy specifies the execution environment for the *command*. Typically, the real and effective user and group and IDs are set to match those of the target user, as specified in the password database, and the group vector is initialized based on the group database (unless the **-P** option was specified).

The following parameters may be specified by security policy:

- ⊕ real and effective user-ID
- ⊕ real and effective group-ID
- ⊕ supplementary group-IDs
- ⊕ the environment list
- ⊕ current working directory
- ⊕ file creation mode mask (umask)
- ⊕ SELinux role and type
- ⊕ Solaris project
- ⊕ Solaris privileges
- ⊕ BSD login class
- ⊕ scheduling priority (aka nice value)

### Process model

There are two distinct ways **sudo** can run a *command*.

If an I/O logging plugin is configured to log terminal I/O, or if the security policy explicitly requests it, a new pseudo-terminal ("pty") is allocated and `fork(2)` is used to create a second **sudo** process, referred to as the *monitor*. The *monitor* creates a new terminal session with itself as the leader and the pty as its controlling terminal, calls `fork(2)` again, sets up the execution environment as described above, and then

uses the `execve(2)` system call to run the *command* in the child process. The *monitor* exists to relay job control signals between the user's terminal and the pty the *command* is being run in. This makes it possible to suspend and resume the *command* normally. Without the *monitor*, the *command* would be in what POSIX terms an "orphaned process group" and it would not receive any job control signals from the kernel. When the *command* exits or is terminated by a signal, the *monitor* passes the *command*'s exit status to the main **sudo** process and exits. After receiving the *command*'s exit status, the main **sudo** process passes the *command*'s exit status to the security policy's close function, as well as the close function of any configured audit plugin, and exits. This mode is the default for sudo versions 1.9.14 and above when using the sudoers policy.

If no pty is used, **sudo** calls `fork(2)`, sets up the execution environment as described above, and uses the `execve(2)` system call to run the *command* in the child process. The main **sudo** process waits until the *command* has completed, then passes the *command*'s exit status to the security policy's close function, as well as the close function of any configured audit plugins, and exits. As a special case, if the policy plugin does not define a close function, **sudo** will execute the *command* directly instead of calling `fork(2)` first. The *sudoers* policy plugin will only define a close function when I/O logging is enabled, a pty is required, an SELinux role is specified, the *command* has an associated timeout, or the *pam\_session* or *pam\_setcred* options are enabled. Both *pam\_session* and *pam\_setcred* are enabled by default on systems using PAM. This mode is the default for sudo versions prior to 1.9.14 when using the sudoers policy.

On systems that use PAM, the security policy's close function is responsible for closing the PAM session. It may also log the *command*'s exit status.

### Signal handling

When the *command* is run as a child of the **sudo** process, **sudo** will relay signals it receives to the *command*. The SIGINT and SIGQUIT signals are only relayed when the *command* is being run in a new pty or when the signal was sent by a user process, not the kernel. This prevents the *command* from receiving SIGINT twice each time the user enters control-C. Some signals, such as SIGSTOP and SIGKILL, cannot be caught and thus will not be relayed to the *command*. As a general rule, SIGTSTP should be used instead of SIGSTOP when you wish to suspend a *command* being run by **sudo**.

As a special case, **sudo** will not relay signals that were sent by the *command* it is running. This prevents the *command* from accidentally killing itself. On some systems, the `reboot(8)` utility sends SIGTERM to all non-system processes other than itself before rebooting the system. This prevents **sudo** from relaying the SIGTERM signal it received back to `reboot(8)`, which might then exit before the system was actually rebooted, leaving it in a half-dead state similar to single user mode. Note, however, that this check only applies to the *command* run by **sudo** and not any other processes that the *command* may create. As a result, running a script that calls `reboot(8)` or `shutdown(8)` via **sudo** may cause the system to end up in this undefined state unless the `reboot(8)` or `shutdown(8)` are run using the `exec()` family of functions

instead of **system()** (which interposes a shell between the *command* and the calling process).

### Plugins

Plugins may be specified via *Plugin* directives in the `sudo.conf(5)` file. They may be loaded as dynamic shared objects (on systems that support them), or compiled directly into the **sudo** binary. If no `sudo.conf(5)` file is present, or if it doesn't contain any *Plugin* lines, **sudo** will use `sudoers(5)` for the policy, auditing, and I/O logging plugins. See the `sudo.conf(5)` manual for details of the `/etc/sudo.conf` file and the `sudo_plugin(5)` manual for more information about the **sudo** plugin architecture.

### EXIT VALUE

Upon successful execution of a *command*, the exit status from **sudo** will be the exit status of the program that was executed. If the *command* terminated due to receipt of a signal, **sudo** will send itself the same signal that terminated the *command*.

If the **-l** option was specified without a *command*, **sudo** will exit with a value of 0 if the user is allowed to run **sudo** and they authenticated successfully (as required by the security policy). If a *command* is specified with the **-l** option, the exit value will only be 0 if the *command* is permitted by the security policy, otherwise it will be 1.

If there is an authentication failure, a configuration/permission problem, or if the given *command* cannot be executed, **sudo** exits with a value of 1. In the latter case, the error string is printed to the standard error. If **sudo** cannot `stat(2)` one or more entries in the user's `PATH`, an error is printed to the standard error. (If the directory does not exist or if it is not really a directory, the entry is ignored and no error is printed.) This should not happen under normal circumstances. The most common reason for `stat(2)` to return "permission denied" is if you are running an automounter and one of the directories in your `PATH` is on a machine that is currently unreachable.

### SECURITY NOTES

**sudo** tries to be safe when executing external *commands*.

To prevent command spoofing, **sudo** checks "." and "" (both denoting current directory) last when searching for a *command* in the user's `PATH` (if one or both are in the `PATH`). Depending on the security policy, the user's `PATH` environment variable may be modified, replaced, or passed unchanged to the program that **sudo** executes.

Users should *never* be granted **sudo** privileges to execute files that are writable by the user or that reside in a directory that is writable by the user. If the user can modify or replace the *command* there is no way to limit what additional *commands* they can run.

By default, **sudo** will only log the *command* it explicitly runs. If a user runs a *command* such as 'sudo

su' or 'sudo sh', subsequent *commands* run from that shell are not subject to **sudo**'s security policy. The same is true for *commands* that offer shell escapes (including most editors). If I/O logging is enabled, subsequent *commands* will have their input and/or output logged, but there will not be traditional logs for those *commands*. Because of this, care must be taken when giving users access to *commands* via **sudo** to verify that the *command* does not inadvertently give the user an effective root shell. For information on ways to address this, see the *Preventing shell escapes* section in `sudoers(5)`.

To prevent the disclosure of potentially sensitive information, **sudo** disables core dumps by default while it is executing (they are re-enabled for the *command* that is run). This historical practice dates from a time when most operating systems allowed set-user-ID processes to dump core by default. To aid in debugging **sudo** crashes, you may wish to re-enable core dumps by setting "disable\_coredump" to false in the `sudo.conf(5)` file as follows:

```
Set disable_coredump false
```

See the `sudo.conf(5)` manual for more information.

## ENVIRONMENT

**sudo** utilizes the following environment variables. The security policy has control over the actual content of the *command*'s environment.

EDITOR	Default editor to use in <b>-e</b> (suedit) mode if neither SUDO_EDITOR nor VISUAL is set.
MAIL	Set to the mail spool of the target user when the <b>-i</b> option is specified, or when <i>env_reset</i> is enabled in <i>sudoers</i> (unless MAIL is present in the <i>env_keep</i> list).
HOME	Set to the home directory of the target user when the <b>-i</b> or <b>-H</b> options are specified, when the <b>-s</b> option is specified and <i>set_home</i> is set in <i>sudoers</i> , when <i>always_set_home</i> is enabled in <i>sudoers</i> , or when <i>env_reset</i> is enabled in <i>sudoers</i> and HOME is not present in the <i>env_keep</i> list.
LOGNAME	Set to the login name of the target user when the <b>-i</b> option is specified, when the <i>set_logname</i> option is enabled in <i>sudoers</i> , or when the <i>env_reset</i> option is enabled in <i>sudoers</i> (unless LOGNAME is present in the <i>env_keep</i> list).
PATH	May be overridden by the security policy.
SHELL	Used to determine shell to run with <b>-s</b> option.

**SUDO\_ASKPASS**

Specifies the path to a helper program used to read the password if no terminal is available or if the **-A** option is specified.

**SUDO\_COMMAND**

Set to the *command* run by sudo, including any *args*. The *args* are truncated at 4096 characters to prevent a potential execution error.

**SUDO\_EDITOR** Default editor to use in **-e** (sdoedit) mode.

**SUDO\_GID** Set to the group-ID of the user who invoked sudo.

**SUDO\_HOME** Set to the home directory of the user who invoked sudo.

**SUDO\_PROMPT** Used as the default password prompt unless the **-p** option was specified.

**SUDO\_PS1** If set, PS1 will be set to its value for the program being run.

**SUDO\_UID** Set to the user-ID of the user who invoked sudo.

**SUDO\_USER** Set to the login name of the user who invoked sudo.

**USER** Set to the same value as LOGNAME, described above.

**VISUAL** Default editor to use in **-e** (sdoedit) mode if **SUDO\_EDITOR** is not set.

**FILES**

*/etc/sudo.conf* **sudo** front-end configuration

**EXAMPLES**

The following examples assume a properly configured security policy.

To get a file listing of an unreadable directory:

```
$ sudo ls /usr/local/protected
```

To list the home directory of user yaz on a machine where the file system holding ~yaz is not exported as root:

```
$ sudo -u yaz ls ~yaz
```

To edit the *index.html* file as user *www*:

```
$ sudoedit -u www ~www/htdocs/index.html
```

To view system logs only accessible to root and users in the *adm* group:

```
$ sudo -g adm more /var/log/syslog
```

To run an editor as *jim* with a different primary group:

```
$ sudoedit -u jim -g audio ~jim/sound.txt
```

To shut down a machine:

```
$ sudo shutdown -r +15 "quick reboot"
```

To make a usage listing of the directories in the */home* partition. The *commands* are run in a sub-shell to allow the 'cd' command and file redirection to work.

```
$ sudo sh -c "cd /home ; du -s * | sort -rn > USAGE"
```

## DIAGNOSTICS

Error messages produced by **sudo** include:

editing files in a writable directory is not permitted

By default, **sudoedit** does not permit editing a file when any of the parent directories are writable by the invoking user. This avoids a race condition that could allow the user to overwrite an arbitrary file. See the *sudoedit\_checkdir* option in *sudoers(5)* for more information.

editing symbolic links is not permitted

By default, **sudoedit** does not follow symbolic links when opening files. See the *sudoedit\_follow* option in *sudoers(5)* for more information.

effective uid is not 0, is sudo installed setuid root?

**sudo** was not run with root privileges. The **sudo** binary must be owned by the root user and have the set-user-ID bit set. Also, it must not be located on a file system mounted with the 'nosuid' option or on an NFS file system that maps uid 0 to an unprivileged uid.

effective uid is not 0, is sudo on a file system with the 'nosuid' option set or an NFS file system without root privileges?

**sudo** was not run with root privileges. The **sudo** binary has the proper owner and permissions but it still did not run with root privileges. The most common reason for this is that the file system the **sudo** binary is located on is mounted with the 'nosuid' option or it is an NFS file system that maps uid 0 to an unprivileged uid.

fatal error, unable to load plugins

An error occurred while loading or initializing the plugins specified in sudo.conf(5).

invalid environment variable name

One or more environment variable names specified via the **-E** option contained an equal sign ('='). The arguments to the **-E** option should be environment variable names without an associated value.

no password was provided

When **sudo** tried to read the password, it did not receive any characters. This may happen if no terminal is available (or the **-S** option is specified) and the standard input has been redirected from */dev/null*.

a terminal is required to read the password

**sudo** needs to read the password but there is no mechanism available for it to do so. A terminal is not present to read the password from, **sudo** has not been configured to read from the standard input, the **-S** option was not used, and no askpass helper has been specified either via the sudo.conf(5) file or the SUDO\_ASKPASS environment variable.

no writable temporary directory found

**sudoedit** was unable to find a usable temporary directory in which to store its intermediate files.

The "no new privileges" flag is set, which prevents sudo from running as root.

**sudo** was run by a process that has the Linux "no new privileges" flag is set. This causes the set-user-ID bit to be ignored when running an executable, which will prevent **sudo** from functioning. The most likely cause for this is running **sudo** within a container that sets this flag. Check the documentation to see if it is possible to configure the container such that the flag is not set.

sudo must be owned by uid 0 and have the setuid bit set

**sudo** was not run with root privileges. The **sudo** binary does not have the correct owner or permissions. It must be owned by the root user and have the set-user-ID bit set.

sudoedit is not supported on this platform

It is only possible to run **sudoedit** on systems that support setting the effective user-ID.

timed out reading password

The user did not enter a password before the password timeout (5 minutes by default) expired.

you do not exist in the passwd database

Your user-ID does not appear in the system passwd database.

you may not specify environment variables in edit mode

It is only possible to specify environment variables when running a *command*. When editing a file, the editor is run with the user's environment unmodified.

## SEE ALSO

su(1), stat(2), login\_cap(3), passwd(5), sudo.conf(5), sudo\_plugin(5), sudoers(5), sudoers\_timestamp(5), sudoreplay(8), visudo(8)

## HISTORY

See the HISTORY.md file in the **sudo** distribution (<https://www.sudo.ws/about/history/>) for a brief history of sudo.

## AUTHORS

Many people have worked on **sudo** over the years; this version consists of code written primarily by:

Todd C. Miller

See the CONTRIBUTORS.md file in the **sudo** distribution (<https://www.sudo.ws/about/contributors/>) for an exhaustive list of people who have contributed to **sudo**.

## CAVEATS

There is no easy way to prevent a user from gaining a root shell if that user is allowed to run arbitrary *commands* via **sudo**. Also, many programs (such as editors) allow the user to run *commands* via shell escapes, thus avoiding **sudo**'s checks. However, on most systems it is possible to prevent shell escapes with the sudoers(5) plugin's *noexec* functionality.

It is not meaningful to run the 'cd' *command* directly via sudo, e.g.,

```
$ sudo cd /usr/local/protected
```

since when the *command* exits the parent process (your shell) will still be the same. The **-D** option can be used to run a *command* in a specific *directory*.

Running shell scripts via **sudo** can expose the same kernel bugs that make set-user-ID shell scripts



unsafe on some operating systems (if your OS has a `/dev/fd/` directory, set-user-ID shell scripts are generally safe).

## BUGS

If you believe you have found a bug in **sudo**, you can either file a bug report in the sudo bug database, <https://bugzilla.sudo.ws/>, or open an issue at <https://github.com/sudo-project/sudo/issues>. If you would prefer to use email, messages may be sent to the sudo-workers mailing list, <https://www.sudo.ws/mailman/listinfo/sudo-workers> (public) or `<sudo@sudo.ws>` (private).

Please not report security vulnerabilities through public GitHub issues, Bugzilla or mailing lists. Instead, report them via email to `<Todd.Miller@sudo.ws>`. You may encrypt your message with PGP if you would like, using the key found at <https://www.sudo.ws/dist/PGPKEYS>.

## SUPPORT

Limited free support is available via the sudo-users mailing list, see <https://www.sudo.ws/mailman/listinfo/sudo-users> to subscribe or search the archives.

## DISCLAIMER

**sudo** is provided "AS IS" and any express or implied warranties, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose are disclaimed. See the LICENSE.md file distributed with **sudo** or <https://www.sudo.ws/about/license/> for complete details.